

# **PSpice Advanced Analysis Known Problems and Solutions**

**Product Version 16.6  
October 2012**

© 1991–2012 Cadence Design Systems, Inc. All rights reserved.

Portions © Apache Software Foundation, Sun Microsystems, Free Software Foundation, Inc., Regents of the University of California, Massachusetts Institute of Technology, University of Florida. Used by permission. Printed in the United States of America.

Cadence Design Systems, Inc. (Cadence), 2655 Seely Ave., San Jose, CA 95134, USA.

Product PSpice Advanced Analysis contains technology licensed from, and copyrighted by: Apache Software Foundation, 1901 Munsey Drive Forest Hill, MD 21050, USA © 2000-2005, Apache Software Foundation. Sun Microsystems, 4150 Network Circle, Santa Clara, CA 95054 USA © 1994-2007, Sun Microsystems, Inc. Free Software Foundation, 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA © 1989, 1991, Free Software Foundation, Inc. Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, © 2001, Regents of the University of California. Daniel Stenberg, © 1996 - 2006, Daniel Stenberg. UMFPACK © 2005, Timothy A. Davis, University of Florida, (davis@cise.ulf.edu). Ken Martin, Will Schroeder, Bill Lorensen © 1993-2002, Ken Martin, Will Schroeder, Bill Lorensen. Massachusetts Institute of Technology, 77 Massachusetts Avenue, Cambridge, Massachusetts, USA © 2003, the Board of Trustees of Massachusetts Institute of Technology. vtkQt, © 2000-2005, Matthias Koenig. All rights reserved.

**Trademarks:** Trademarks and service marks of Cadence Design Systems, Inc. contained in this document are attributed to Cadence with the appropriate symbol. For queries regarding Cadence's trademarks, contact the corporate legal department at the address shown above or call 800.862.4522.

Open SystemC, Open SystemC Initiative, OSCI, SystemC, and SystemC Initiative are trademarks or registered trademarks of Open SystemC Initiative, Inc. in the United States and other countries and are used with permission.

All other trademarks are the property of their respective holders.

**Restricted Permission:** This publication is protected by copyright law and international treaties and contains trade secrets and proprietary information owned by Cadence. Unauthorized reproduction or distribution of this publication, or any portion of it, may result in civil and criminal penalties. Except as specified in this permission statement, this publication may not be copied, reproduced, modified, published, uploaded, posted, transmitted, or distributed in any way, without prior written permission from Cadence. Unless otherwise agreed to by Cadence in writing, this statement grants Cadence customers permission to print one (1) hard copy of this publication subject to the following conditions:

1. The publication may be used only in accordance with a written agreement between Cadence and its customer.
2. The publication may not be modified in any way.
3. Any authorized copy of the publication or portion thereof must include all original copyright, trademark, and other proprietary notices and this permission statement.
4. The information contained in this document cannot be used in the development of like products or software, whether for internal or external use, and shall not be used for the benefit of any other party, whether or not for consideration.

**Disclaimer:** Information in this publication is subject to change without notice and does not represent a commitment on the part of Cadence. Except as may be explicitly set forth in such agreement, Cadence does not make, and expressly disclaims, any representations or warranties as to the completeness, accuracy or usefulness of the information contained in this document. Cadence does not warrant that use of such information will not infringe any third party rights, nor does Cadence assume any liability for damages or costs of any kind that may result from use of such information.

**Restricted Rights:** Use, duplication, or disclosure by the Government is subject to restrictions as set forth in FAR52.227-14 and DFAR252.227-7013 et seq. or its successor

---

# Contents

---

<u>Known Problems and Solutions in Advanced Analysis</u> .....	5
<u>CCR 153216: Incorrect plot is displayed if the outer sweep variable has a single value</u> 5	
<u>CCR 174349: Advanced Analysis tools do not run if the csdf option set.</u> .....	5
<u>CCR 20199: Fewer data points in Advanced Analysis Optimizer .DAT file</u> .....	6
<u>CCR 23833: Simulation server (Simsrvr) may crash if Advanced Analysis is invoked</u> <u>during pause</u> .....	6
<u>Known Problems and Solutions in Capture-Advanced Analysis and Design Entry HDL -</u> <u>Advanced Analysis Flows</u> .....	6
<u>CCR 32518: Smoke analysis: Need to change SOURCE_PACKAGE property value to</u> <u>match IMPLEMENTATION property value if you edit smoke information in a part</u> ....	7
<u>CCR 32420: Changes in device parameters are not being recognized by PSpice</u> <u>Advanced Analysis</u> .....	7

## **PSpice Advanced Analysis Known Problems and Solutions**

---

---

# PSPice Advanced Analysis Known Problems and Solutions

---

This Known Problems and Solutions document describes important Cadence Change Requests (CCRs) for Advanced Analysis and tells you how to solve or work around these problems. For information about CCRs that are fixed for this release, see Advanced Analysis<sup>1</sup> Product Notes.

**Important:** Only known problems and solutions available at release time are available in this document.

## Known Problems and Solutions in Advanced Analysis

This section lists the known problems in Advanced Analysis and tells you how to solve or work around these problems.

### **CCR 153216: Incorrect plot is displayed if the outer sweep variable has a single value**

**Description:** In Parametric Plot analysis if the outer sweep variable has a single value, and it is set as X axis in the plot definition, the correct trace will not be displayed.

**Solution:** To view the correct plot, turn off the performance analysis from PSPice UI. Then bring up the Add trace dialog, and select the variable defined as Y axis. Next, add the trace.

### **CCR 174349: Advanced Analysis tools do not run if the csdf option set.**

**Description:** To evaluate expressions, Advanced Analysis tools such as Optimizer, Parametric Plotter, Monte Carlo, and Sensitivity use the data file after every run. Therefore, if the csdf option is set these tools are not able to run.

---

1. Depending on the license you will either access PSPice Advanced Analysis or AMS Simulator Advanced Analysis.

## PSpice Advanced Analysis Known Problems and Solutions

### October 2012

**Solution:** Before running advanced analysis on the design, ensure that the *Save data in the CSDF format (.CSD)* check box, in the Data Collection tab of the Simulation Settings dialog box is clear.

#### **CCR 20199: Fewer data points in Advanced Analysis Optimizer .DAT file**

**Description:** When running an optimization that uses an AC sweep, it is possible for the highest frequency data point to not be written to the .DAT file. As a consequence, a measurement that uses the last data point (highest frequency) will fail to be evaluated.

**Solution:** Either specify more points (higher resolution) for the AC sweep or increase the highest frequency for the sweep, so that the measurement does not use the highest frequency point.

#### **CCR 23833: Simulation server (Simsrvr) may crash if Advanced Analysis is invoked during pause**

**Description:** Advanced Analysis uses simulation profiles that are set up for the PSpice project. If you run one of these simulation profiles, the status of the simulation will be displayed in the PSpice Simulation Manager. If a simulation profile is Paused and then one of the Advanced Analysis tools is invoked, the Simulation server may crash.

**Solution:** Before invoking Advanced Analysis, be sure to check that there are no paused simulations in the PSpice Simulation Manager for the circuit. To do this, go to the Windows system tray, which is located in the lower right corner of your computer screen. Double-click the PSpice Simulation Manager icon (hover your mouse over the icon shaped like a yellow square to check the icon name). In the PSpice Simulation Manager window, right-click on any paused simulations, and then choose Stop.

## **Known Problems and Solutions in Capture-Advanced Analysis and Design Entry HDL -Advanced Analysis Flows**

This section lists the important Cadence Change Requests (CCRs) in using Capture or Design Entry HDL with Advanced Analysis and tells you how to solve or work around these problems.

### **CCR 32518: Smoke analysis: Need to change SOURCE\_PACKAGE property value to match IMPLEMENTATION property value if you edit smoke information in a part**

If you edit the model for a part placed in your design and change its smoke parameters, you must change the value of the SOURCE\_PACKAGE property on the part to match the value of the IMPLEMENTATION property on the part.

To change the value of the SOURCE\_PACKAGE property on the part, do the following:

1. Select the part on the schematic page.
2. From the Edit menu, choose Part.  
The part editor window appears.
3. From the Options menu, choose Package Properties.  
The Edit Part Properties dialog box appears.
4. In the Name text box, enter the name of the model that is specified as the value of the IMPLEMENTATION property on the part.
5. Click OK.
6. From the File menu, choose Close.
7. Click Update All in the Save Part Instance message box that appears.

**Note:** If the value of the SOURCE\_PACKAGE property is not the same as the value of the IMPLEMENTATION property, the modified smoke information will not be used for smoke analysis. Instead, the smoke information from the part library will be used for smoke analysis.

### **CCR 32420: Changes in device parameters are not being recognized by PSpice Advanced Analysis**

**Description:** This problem occurs when you open a PSpice model from Capture and change its device parameters in Model Editor or change device parameters on a part instance in Capture. When you run PSpice Advanced Analysis, you will notice that the new parameters are not visible.

**Solution:** From the PSpice menu in Capture, choose Create Netlist, then run Advanced Analysis.

# **PSpice Advanced Analysis Known Problems and Solutions**

## **October 2012**